

Copyright 2002 HP

Product Name: NonStop AutoTMF

Product ID: SA45V1

Component Products: T0581V03 NonStop AutoTMF

I. Basic Product Installation Instructions

1. Ensure that requirements for using this product are met (see Section IV Product Requirements below).
2. Ensure that prerequisites for the installation utility and any product-specific installation requirements are met (see Section V Installation Prerequisites below).
3. Review the file USRGUIDE.PDF (in the subdirectory NSK_SW on this CD) containing the IPSetup User Guide, which provides instructions for using IPSetup, a utility provided on the CD that enables installation of Independent Products. You need Adobe Acrobat Reader (available on this CD) to read or print the IPSetup User Guide.
4. Decide whether you will use DSM/SCM to move files to Installation Subvolumes (ISVs) after files are placed on the workstation. Using DSM/SCM is optional, but is recommended when DSM/SCM is available.
5. Follow the pre-installation instructions in Section II below, if any, before continuing to Step 6.
6. Run IPSetup to place (move files from the CD to the workstation) and install (move NonStop Kernel files to correct ISVs) this product. If TCP/IP and FTP are unavailable, or if you have problems with automatic file placement, use the instructions in the IPSetup User Guide section "Manual Software Placement Using the IPSetup TACL Program" to manually place NonStop Kernel files.
7. Once the files have been moved to the ISV (ZAUTOTMF) on the NonStop Himalaya server, volume to the ISV and run the ZAUTOTMF.INSTALL macro.
See the SOFTDOC for details.

II. Pre-Installation Instructions

None

III. Post-Installation Instructions

See SOFTDOC for instructions.

IV. Product Requirements

Required Hardware:

NonStop System

Minimum OS Release:

See SOFTDOC for release levels.

Required Software:

Disk Space Requirement:

- 40 MB in DSV
- 40 MB in ISV
- 15 MB per AutoTMF subvolume
- 1 MB for AutoTMF Configuration

V. Installation Prerequisites

Required Hardware:

- NonStop Himalaya server
- Communications controller allowing file transfer from PC to NonStop Himalaya server

PC with 486 or higher processor and all of the following:

- CD-ROM drive
- VGA or higher-resolution video adapter and monitor
- Microsoft Mouse or similar pointing device
- Communications controller allowing file transfer from PC to NonStop Himalaya server

Required Software:

- T9550D30 SOCKET LIBRARY or higher version
- T9552D30 TCP/IP FTP with IPM ABG or superseding IPM (for releases D31.00 to D40.00)
- T9552D40 TCP/IP FTP with IPM ABJ or superseding IPM (for releases D40.01 and higher)
- Microsoft Windows 95, or Windows NT 4.0 or later
- Microsoft TCP/IP stack and FTP client

VI. Manuals Included On this CD

None

VII. CD-ROM Root Directory Contents

AUTORUN.INF	File containing CD AutoRun commands
AXDIST.EXE	Microsoft Redistributable Library Files
IPSETUP.CNT	File containing help contents for the CD installation utility IPSetup.
IPSETUP.EXE	File containing the main executable for IPSetup.
IPSETUP.HLP	File containing help text for IPSetup.
LICENSE.TXT	File containing limited-use Software Licensing Agreement with the licensing terms governing this product.
README.TXT	File containing product and installation information (this file).
SETUP.EXE	File containing the Launcher executable.
SOFTDOCS	Subdirectory containing all Product Version and Product Version Update

Softdocs.

NSK_SW Subdirectory containing NonStop Kernel component files, including installation utilities and instructions.

WS_SW Subdirectory containing workstation component files (if applicable to this product), including installation utilities if any.

CD_DOCS Subdirectory containing product documentation in the following two subdirectories:

TIM_COLL Subdirectory of CD_DOCS containing product manuals formatted for the Total Information Manager (TIM) viewer.

PDF_DOCS Subdirectory of CD_DOCS containing:

1. Product manuals in PDF format for viewing with Adobe Acrobat Reader
2. ACROBAT_VIEWERS subdirectory containing Adobe Acrobat Reader.