

Copyright 2004 HP

Product Name: NonStop AutoSYNC

Product ID: SA46V1 Update 3

Component Products: T2713V11^AAC

## I. Basic Product Installation Instructions

1. Ensure that requirements for using this product are met (see Section IV Product Requirements below).
2. Ensure that prerequisites for the installation utility and any product-specific installation requirements are met (see Section V Installation Prerequisites below).
3. Review the file USRGUIDE.PDF (in the subdirectory NSK\_SW on this CD) containing the IPSetup User Guide, which provides instructions for using IPSetup, a utility provided on the CD that enables installation of Independent Products. You will need Adobe Acrobat Reader to read or print the IPSetup User Guide. Visit Adobe's website to download the latest Adobe Acrobat Reader:  
<http://www.adobe.com>
4. Decide whether you will use DSM/SCM to move files to Installation Subvolumes (ISVs) after files are placed on the workstation. Using DSM/SCM is optional, but is recommended when DSM/SCM is available.
5. Follow the pre-installation instructions in Section II below, if any, before continuing to Step 6.
6. Run IPSetup to place (move files from the CD to the workstation) and install (move NonStop Kernel files to correct ISVs) this product. If TCP/IP and FTP are unavailable, or if you have problems with automatic file placement, use the instructions in the IPSetup User Guide section "Manual Software Placement Using the IPSetup TACL Program" to manually place NonStop Kernel files.

This product contains both NonStop Kernel components and workstation components. You must place each component type separately. To restart the installation program after placing the first component type, click SETUP.EXE in the root directory.

**IMPORTANT:** Always reinstall this product after using the Install product to install a Site Update Tape (SUT). Installing a SUT using the Install product can result in overwriting this Independent Product with older versions of software. This problem does not occur when using DSM/SCM to install SUTs.

7. Follow the post-installation instructions in Section III below, if any, after using IPSetup to place and install this product.

## II. Pre-Installation Instructions

NONE

### III. Post-Installation Instructions

See SOFTDOC for instructions.

### IV. Product Requirements

#### Required Hardware:

RISC-based HP NonStop Server

#### Minimum OS Release:

See SOFTDOC for Release levels.

#### Required Software: NONE

#### Disk Space Requirement:

40 MB in DSV

40 MB in ISV

15 MB per AutoSYNC subvolume

1 MB for AutoSYNC Configuration

### V. Installation Prerequisites

#### Required Hardware:

RISC-based HP NonStop server

Communications controller allowing file transfer  
from PC to HP NonStop Server

PC with 486 or higher processor and all of the following:

CD-ROM drive

VGA or higher-resolution video adapter and monitor

Microsoft Mouse or similar pointing device

Communications controller allowing file transfer  
from PC to HP NonStop server

#### Required Software:

T9550D30 SOCKET LIBRARY or higher version

T9552D30 TCP/IP FTP with IPM ABG or superseding IPM  
(for releases D31.00 to D40.00)

T9552D40 TCP/IP FTP with IPM ABJ or superseding IPM  
(for releases D40.01 and higher)

Microsoft Windows 95, or Windows NT 4.0 or later

Microsoft TCP/IP stack and FTP client

### VI. Manuals Included On this CD

522580-004 HP NonStop AutoSYNC User's Guide

### VII. CD-ROM Root Directory Contents

AUTORUN.INF File containing CD AutoRun commands.

AXDIST.EXE Microsoft redistributable library files.

IPSETUP.CNT File containing help contents for the CD installation  
utility IPSetup.

IPSETUP.EXE File containing the main executable for IPSetup.

IPSETUP.HLP File containing help text for IPSetup.

LICENSE.TXT File containing limited-use Software Licensing Agreement with the licensing terms governing this product.

README.TXT File containing product and installation information (this file).

SETUP.EXE File containing the Launcher executable.

NSK\_SW Subdirectory containing NonStop Kernel component files, including installation utilities and instructions.

WS\_SW Subdirectory containing workstation component files (if applicable to this product), including installation utilities if any.

SOFTDOCS Subdirectory containing all Initial Product Version / Product Version Update Softdocs.

CD\_DOCS Subdirectory containing product documentation in the following subdirectories:

PDF\_DOCS Subdirectory of CD\_DOCS containing:

1. Product manuals in PDF format for viewing with Adobe Acrobat Reader
2. ACROBAT\_VIEWER providing Adobe URL for downloading the latest Adobe Acrobat Reader.  
Visit Adobe's website at <http://www.adobe.com>